

WIN CE LAGER / WIN CE MOBILE DATA is a data capturing software for mobile devices with operating system Windows CE 5.0 (or higher) and with QVGA display resolution in 240 x 320 pixels.

This software is easy and normally self explaining. If you need a user manual – see here:

<http://terminal-systems.de/wince-lager/doc-wincemobiledata-en.pdf>

Using at a mobile data terminal:

download the ZIP file from our website, unpack it into a folder at your local PC and transfer the EXE software to your mobile data terminal. Start the EXE at your data terminal. Ready!

Using at a PC:

Modern technology allows the usage of this software package at a Windows based PC system. So you can test it if you do not have any MDT hardware at the moment. The software will normally run without any problems but of course it will be used with small windows (based on the smaller display on the mobile device). This further document will give you some hints how to use it at your PC....

Note for DEMO version:

The demoversion without license is limited at some items only and the saved quantity / value for each item will be automatically set to 99. This will disappear if you use the licensed full version of the software.

PC Installation

Step 1: Start your explorer, create a folder for your software e.g. names as WINCELAGER

Important: Keep the name and location of your folder in mind!

Step 2: Copy and unpack the ZIP content into your new folder

Step 3: Start the programm / EXE file with name WinCELager-??.EXE / WinCeMobileData-??.EXE

Use the version where ?? represents the desired language function, e.g for EN or US for english version!

If the software does not start: maybe the Microsoft DOT NET framework is missing at your PC! Check this.

PC: Simulate Handheld Environment

This is important because normally there are some technical differences between your desktop PC and handheld device. The handheld device saves the data in a /TEMP directory – direct from the root folder.

Step 4: Create a /TEMP folder direct in your root

Step 5: Save your article host file ARTIKEL.TXT inside folder /TEMP

After you have done this and start the software (see step 3!) the artikel host file will be use as information base during manual input. After reading a barcode / input article no the article text will be presented inside display etc.

Step 6: Process with your input data

All your inputs will be stored inside a file BUCHUNG.XLS inside the /TEMP folder. You can use this file for data processing your PC.

Using

If you have a mobile handheld device such as a MDT system you can use touch screen or cursor keys for navigate inside your software. Input will be confirmed with the ENTER key, a BACK function will be activated with the ESC key. This allows an easily navigating for the user.

During your PC: use ESC and ENTER for backwards or confirming data. Use cursor keys UP and DOWN for selection – and ENTER key for start something...

File

/TEMP/BUCHUNG.XLS
Manual input information from the user

/TEMP/ARTIKEL.TXT
Article HOST file.